

Smart Construction Fleet Release Note

App Ver : **5.10.0**

Scheduled Release : **October 1st (Tuesday), 18:00 to 20:00 (JST)**

We are planning to release new features for Smart Construction Fleet.

※Please note that we will not be releasing this update for the Classic version this time.



クラシック版



<<The feature to be added this time>>

- [Web] Make "Operational Vehicle Daily Report" always available to check on the Web app
- [Web] Make it possible to download the Excel file for "Operational Vehicle Daily Report"
- [Web] Make it possible to send login links and 2D codes by email
- [Web] Make it possible to set planning values (frequency and soil volume) for each workplace
- [Web] Add a widget in the real-time viewer to display the frequency and soil volume for each work site in the form of actual/planned values

<< Minor adjustments >>

- [Web] Change the "Copy login link to clipboard" button to a more user-friendly design.
- [Web] When issuing individual login codes for certain vehicle types, the role will be automatically selected
- [Mobile] In some vehicle types, the role will be automatically selected when logging in

A pre-update of the mobile app is not mandatory for this release.

We have included instructions on how to set up automatic updates on iPhone at the [end of this document](#).

Please feel free to use them as needed.

The mobile app is scheduled for store release on Monday, September 30th.

※The timing of the mobile app's store release may vary depending on the review process.


During operations at active sites, please note the following partial restrictions:

Web or Mobile	Influence
Web	Cannot log in
Web	If you are logged in on the mobile app or dedicated device, an error will occur at the next server access.
Web	In the Real-time viewer , an error will be displayed.
Mobile	Cannot log in
Mobile	When logged in, an error occurs when attempting to retrieve the location information of other vehicles on the map.
Mobile	An error occurs when switching tabs.
Mobile	During server downtime, location information is stored on the device. Once the server is back online, the stored location information will be sent out gradually.
Mobile	Detection of entry into alert points operates normally.
Mobile	Detection of entry into workplace and approaching notification is not functioning properly.

Scheduled Release : October 1st (Tuesday), 18:00 to 20:00 (JST)



Additional Features / Changes (Web)



vehicledailyreport-27-20240923 (1... • この PC に保存済み)

ファイル ホーム 挿入 ページレイアウト 数式 データ 校閲 表示 自動化 開発 ヘルプ

BY23

Operational Vehicle Daily Report	
Date and Time	2024/09/23 07:00-21:00
Total number of units	19Units
Transport volume	8494.7m3
Weather	<input type="text"/>

Please enter the weather manually as needed.


Daily Report | 1.BB_Fr_Richelieu | 2.BB_HMS_Nelson | 3.CL_HMAS_Perth | 4.CL_Hr. Ms_De I ...

Operational Vehicle Daily Report (per vehicle)

Vehicle name: BB_Fr_Richelieu
 Type: Rigid Dump Truck
 Type of Work:
 Model:
 Management Number:
 Registration Number:
 Driver's Name:
 Assistant's Name:

Speed Distribution

Start Date and Time: 2024/09/23 08:00
 End Date and Time: 2024/09/23 17:56



Task type

Category	Time	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	Total
Move																										0:20
Work																										8:00
Break																										1:00
																										9:20

Travel distance

Category	Travel distance(km)
Move	0.5
Work	186.4
Total Mileage	186.9

Unloading History

Date and Time	Unloading Work Location
2024/09/23 08:15	新地地庫
2024/09/23 08:42	新地地庫
2024/09/23 09:08	新地地庫
2024/09/23 09:35	新地地庫
2024/09/23 10:01	新地地庫
2024/09/23 10:28	新地地庫
2024/09/23 10:55	新地地庫
2024/09/23 11:22	新地地庫
2024/09/23 11:48	新地地庫
2024/09/23 12:15	新地地庫
2024/09/23 13:41	新地地庫
2024/09/23 14:08	新地地庫
2024/09/23 14:35	新地地庫
2024/09/23 15:02	新地地庫
2024/09/23 15:29	新地地庫
2024/09/23 15:56	新地地庫
2024/09/23 16:23	新地地庫
2024/09/23 16:51	新地地庫
2024/09/23 17:18	新地地庫
2024/09/23 17:45	新地地庫
Transportation Frequency	20

Vehicle information, driver information, etc.
 After downloading, you can add or delete fields as needed.

Speed distribution
 Start date and time → Time of login
 End date and time → Time of logout

Job classification
 When selecting a Job classification in the mobile app, the corresponding color is applied.

Travel distance
 Displays the travel distance for each work classification and the total travel distance.






Unload history
 If unloading work is performed in the "Transport" role, a list of the history is displayed.
 The history is displayed according to the "Manual/Automatic" selection status in the web app.

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	R	S	T	U
1	Time	Speed(km/h)																			
41	08:01:57	0																			
42	08:02:00	0																			
43	08:02:03	1																			
44	08:02:06	1																			
45	08:02:09	3																			
46	08:02:12	6																			
47	08:02:15	7																			
48	08:02:18	25																			
49	08:02:21	20																			
50	08:02:24	12																			
51	08:02:27	3																			
52	08:02:30	0																			
53	08:02:33	7																			
54	08:02:36	14																			
55	08:02:39	15																			
56	08:02:42	18																			
57	08:02:45	33																			
58	08:02:48	42																			
59	08:02:51	47																			
60	08:02:54	50																			
61	08:02:57	51																			
62	08:03:00	50																			
63	08:03:03	51																			
64	08:03:06	49																			
65	08:03:09	45																			
66	08:03:12	41																			
67	08:03:15	31																			

Travel Speed Data Sheet

The speed distribution graph displayed on each vehicle's sheet is created based on the values in the data sheet.

If the data sheet is unnecessary, please hide it.



[Email Sending Procedure]

1. Press the "Login Code" button
You can generate the login code using any of the following methods:
 - From the top of each menu screen
 - From "Vehicle Settings"
 - From "Group Settings"
2. Press "Send Email"
3. Enter the recipient
You can add recipients by clicking the "+" button.
4. Press "Send"

Fleet 施工現場 Login code 受信トレイ x

A

fleet_login_code@smartconstruction.com

To 自分 ▼

This is the 2D code to log in to SMART CONSTRUCTION Fleet.

If you want to log in on this device, please click [here](#) — B


If you want to log in on another device, please scan the 2D code.

Fleet 施工現場 A



[Email Explanation]

- A) The site name will be automatically entered in this section.
- B) When opening the link, the Fleet app will launch and navigate to the login screen. If the Fleet app is not installed on the device, it will redirect to the store page.



1 Vehicle list

Vehicle name / Speed	Group	Location / Material	Radius	Role	Battery level
BB Fr Richelieu				Transport	
BB HMS Nelson				Transport	
CL HMAS Perth				Transport	
CL Hr. Ms De Ruyter				Transport	
CL Sv.HMS Gotland				Transport	

Loading (Actual/Planned)

	01/10/2024		Cumulative(23/06/2023 - 31/12/2025)	
	Number of times	Material volume[m3]	Number of times(Performance/Plan)	Material volume(Performance/Plan)[m3]
Total	0	0	70,044 / 88,000	1,627,968 / 2,120,000
荷込地点1	0	0	38,330 / 50,000	374,970 / 500,000
荷込地点2	0	0	24,586 / 30,000	1,164,294 / 1,500,000
荷込地点3	0	0	7,128 / 8,000	88,704 / 120,000

Unloading (Actual/Planned)

	01/10/2024		Cumulative(23/06/2023 - 31/12/2025)	
	Number of times	Material volume[m3]	Number of times(Performance/Plan)	Material volume(Performance/Plan)[m3]
Total	0	0	62,893 / 110,000	1,537,236 / 1,950,000
荷降地点1	0	0	15,491 / 30,000	84,340 / 150,000
荷降地点2	0	0	22,410 / 50,000	1,226,478 / 1,500,000
荷降地点3	0	0	24,992 / 30,000	226,417 / 300,000

2 UI Display Toggle

- Standard
- Google Maps
- Aerial Photography
- Label
- Route Label
- Work Location Label
- Alert Label
- Proximity Notification Label
- Vehicle list
- Vehicle-specific shooting images
- Vehicle-specific cycle time
- Point-specific cycle time
- Loading (today)
- Loading (cumulative)
- Loading (Actual/Planned)
- Unloading (today)
- Unloading (cumulative)
- Unloading (Actual/Planned)
- Sankey diagram

[Widget Display Procedure]


1. Press "Real-time Viewer"
2. Press "UI Display Toggle" in the upper right corner of the screen.
3. Check "Loading (Actual/Planned)" and "Unloading (Actual/Planned)"
4. The widgets will be displayed, so adjust their position and size as needed


Current



When opening the link, the Fleet app will launch and navigate to the login screen. If the Fleet app is not installed on the device, it will redirect to the store page.

After Release







Type	Name	Vehicle weight(kg)	Maximum load volume(m ³)	Maximum load capacity(m ³)	Proximity warning	Proximity warning range(m)	Daily transport plan number	Login code	Use
Articulated Dump Truck	CL_HMAS_Perth	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	CL_Hc_Ms_De_Ruyter	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	CL_R_G.Garibaldi	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	CL_R_Ld.S.D.d.Abruzzi	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	CL_Sv.HMS_Gotland	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	CL_USS_Atlanta	35,400	40,000	24	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	五十鈴	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	北上	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	名取	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	夕張	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	多摩	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	大井	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>
Articulated Dump Truck	大塚	26,185	28,000	17.1	<input checked="" type="checkbox"/>	50	20	[QR Code]	<input checked="" type="checkbox"/>

When generating a vehicle-specific login code from "Vehicle Settings," for some vehicle types, the role will be automatically selected. By scanning the login code with a pre-selected role, users can skip the step of choosing a role in the mobile app.


Type of vehicle	Role(Auto Select)
Dump truck	Transport
Articulated dump truck	Transport
Crawler dump	Transport
Rigid dump truck	Transport
Motor scraper	Specified at login
Tractor	Specified at login
Tank truck	Specified at login
Mixer	Specified at login
Garbage truck	Specified at login
Low-floor trailer	Specified at login
Bus	Others
Van	Others
Commercial van	Others
Excavator	Specified at login
Bulldozer	Specified at login
Wheel loader	Specified at login
Motor grader	Others
Road roller	Others
Forklift truck	Others
Rotary vehicle	Specified at login
Snow removal truck	Transport
Road patrol vehicle	Others
Guide	Others
Camera	Others



In the case of off-road dump



In the case of motor grader




1

Additional Features / Changes (Mobile)



When issuing a login code from "Real-Time Viewer" or "Group Settings" with "Leave it to us" selected, for some vehicle types, the step of selecting a role in the mobile app can be skipped.






Type of vehicle	Role(Auto Select)
Dump truck	Transport
Articulated dump truck	Transport
Crawler dump	Transport
Rigid dump truck	Transport
Motor scraper	Specified at login
Tractor	Specified at login
Tank truck	Specified at login
Mixer	Specified at login
Garbage truck	Specified at login
Low-floor trailer	Specified at login
Bus	Others
Van	Others
Commercial van	Others
Excavator	Specified at login
Bulldozer	Specified at login
Wheel loader	Specified at login
Motor grader	Others
Road roller	Others
Forklift truck	Others
Rotary vehicle	Specified at login
Snow removal truck	Transport
Road patrol vehicle	Others
Guide	Others
Camera	Others



Appendix



On iPhone, by pre-setting the following, the app will be automatically updated via mobile data when updated in the store.


3

6
4
5

7

✓ **Android devices may have different settings menus depending on the manufacturer**

1. Open the "Settings" app
2. Tap on "iTunes & App Store"
3. Turn on "App Updates"
4. Turn on "Automatic Downloads"
If this option is turned off, automatic updates will only occur when connected to Wi-Fi.
5. Tap on "App Downloads"
6. Choose "Always Allow"
7. Setting is finished